

# Injecting to InfluxDB directly from a Compactlogix PLC

## Contents

1. HTTP Library .....	1
1.1. Installing InfluxDB on windows .....	42
1.2. Inject your first data with node-red .....	44
1.3. Injecting in InfluxDB directly from PLC.....	49

## 1. HTTP Library

You can see the final result on this video

<https://youtu.be/UafsIB52IMU>

PLC has DHCP address 192.168.1.41 connected thru a patchcord to the router.

Computer is connected the router thru wifi.

Computer has wifi DHCP address 192.168.1.163

You can find this AOI RM-raC\_Opr\_HTTP on this library "CommonApplicationLibraries\_20230415"





































This belongs to Common application library to be download from Rockwell download page.

<https://compatibility.rockwellautomation.com/pages/search.aspx?crumb=117&q=Common%20ApplicationLibraries%20-%20April%202023>

The screenshot shows the Rockwell Automation website interface. At the top, there is a navigation bar with the Rockwell Automation logo and links for Products, Services, Industries & Solutions, Support, and Sales & Partners. Below this is a secondary navigation bar with icons for lightning bolt, Wi-Fi, Import, and Views, along with a 'Downloads' button. The main content area displays search results for 'Common Application Libraries - April 2023'. The results show a single item: 'Common Application Libraries - April 2023' with a description: '[Download] - Applies to Studio 5000 Application Code Manager 4.03.00, Machine Builder Libraries Current, Power Device Library 3.02.00, Independent Cart Technology Libraries Current, Common Application Libraries Current, Robotics Libraries Current'. There are buttons for 'Download' and 'Add To Download Cart'. On the right side, there is a 'Results' sidebar with a list of filters: All (1), Products (0), Downloads (1), Features (0), Related Products (0), Categories (0), Families (0), and Standard Views (0).

## DOWNLOADS







[SELECTIONS](#)
[COMPARE](#)
[LEGEND](#)

		Studio 5000 Logix Designer		FactoryTalk View Machine Edition		FactoryTalk View Site Edition		RapidLaunch		
show all versions	Downloads	35.00.02	34.02.01	34.01.00	34.00.00	33.02.01	33.01.01	33.00.02	32.04.00	32.03.01
<div><div>Machine Builder Libraries</div><div><div>Current</div><div>Tested, documented and life-cycle managed library objects and faceplates for use with Studio 5000 Application Code Manager (ACM). Machine Builder Libraries contains application objects for a variety of commonly used functions. Content is available for Logix processors, FactoryTalk View SE/ME, and View Designer.</div></div></div>	<div><div></div> <div>Select Files</div> <div><input type="checkbox"/> Firmware Only</div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>
<div><div>Independent Cart Technology Libraries</div><div><div>Current</div><div>Tested, documented and life-cycle managed Independent Cart Technology Libraries for ITRAK and MagneMotion including MagneMover LITE and QuickStick in Studio 5000 Application Code Manager (ACM). The Independent Cart Library also provides pre-configured status and diagnostic HMI faceplates for FactoryTalk View ME.</div></div></div>	<div><div></div> <div>Select Files</div> <div><input type="checkbox"/> Firmware Only</div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>
<div><div>Common Application Libraries</div><div><div>Current</div><div>Commonly used application library objects and faceplates for use with Studio 5000 Application Code Manager (ACM)</div></div></div>	<div><div></div> <div>Select Files</div> <div><input type="checkbox"/> Firmware Only</div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>
<div><div>Studio 5000 Application Code Manager</div><div><div>4.03.01</div></div></div>	<div><div></div> <div>Select Files</div> <div><input type="checkbox"/> Firmware Only</div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>	<div></div>

You will get these content on C:\RA

## Download


Windows (C:) > RA > Common application libraries

Name	Date modified	Type	Size
 ApplicationCodeManagerLibraries	4/14/2023 9:44 PM	File folder	
 GeneralDocuments	4/14/2023 9:33 PM	File folder	
 ReferenceManuals	4/14/2023 9:44 PM	File folder	
 CommonApplicationLibraries_20230415	7/29/2023 5:38 PM	ZIP archive	15,609 KB
 ReadMe	8/24/2022 7:26 PM	Text Document	1 KB
 Setup	8/24/2022 7:25 PM	Windows Command ...	5 KB


Run Setup in order to install the libraries on ACM

Open ACM

Create a new project



Object configuration Wizard will open



Unfold the Project

Click on the yellow area

Object Configuration Wizard ? ×

Select a library

Filter:  ☐ Show All Revisions ☐ Show All Libraries

Solution	LibraryType	Category	CatalogNumber	Family	ContentType	Class	Status
[-] Project (1 item)							
(RA-LIB) ACM 2.00	Project	Project	Basic_Project ( 2.0 )	Project	Task	Standard	Published

<  >

Click on Next

## Select a library

Filter:  ☐ Show All Revisions ☐ Show All Libraries

Solution	LibraryType	Category	CatalogNumber	Family	ContentType	Class	Status
Project (1 item)							
(RA-LIB) ACM 2.00	Project	Project	Basic_Project ( 2.0 )	Project	Task	Standard	Published

<  >

## Library Description:

Basic Project Library

Cancel

&lt;&lt; Previous

Next &gt;&gt;

Finish

Give a name

Object Configuration Wizard



























































**Name:**  **The name "" is invalid or already used for a Project**

**Description:**

**Catalog Number:** Basic\_Project (2.0) - Published

**Solution:** (RA-LIB) ACM 2.00

Parameters

Click on finish

Object Configuration Wizard

**Name:** HTTP

**Description:** Basic Project Library


**Catalog Number:** Basic\_Project (2.0) - Published

**Solution:** (RA-LIB) ACM 2.00


Parameters

Cancel << Previous Next >> Finish

Now you have this blank work space



Add a new controller



Choose your PLC with Machine option (this will create the tasks)



Object Configuration Wizard ? ×

Select a library

Filter:  ☐ Show All Revisions ☐ Show All Libraries

Solution	LibraryType	Category	CatalogNumber	Family	ContentType
[-] Compact GuardLogix (2 items)					
(RA-LIB) ACM 2.00	Controller	Compact GuardLogix	CompactGuardLogix_Controller ( 2.2 )	Logix	Task
(RA-LIB) Machine	Controller	Compact GuardLogix	MachineBuilder_CompactGuardLogix ( 2.2 )	Logix	Task
[-] CompactLogix (2 items)					
[-] ControlLogix (2 items)					
[-] GuardLogix (2 items)					

<  >

Give a name, software revision, controller type and Ethernet Port configuration. Click on finish

## Object Configuration Wizard

**Name:**

**Description:**

**Catalog Number:**

**Solution:**

---

**Parameters**

01 - Controller	
SoftwareRevision	35
ProcessorType	5069-L320ERMS2
EtherNetIPMode	A1/A2: Linear/DLR
02 - HMI	
AreaPath	/Area:[shortcut]
03 - Historian	
HistorianPath	Application/Area:RSLinx Enterprise:[shortcut]
FTLDInterfaceNo	1
Motion	
ConfigureMotion	False
Port Configuration	
EthernetPort1_Enabled	True
EthernetPort2_Enabled	True
Safety Configuration	
Safety_LockApplication	False

**EtherNetIPMode**

Cancel << Previous Next >> Finish

The new controller is created, with it's tasks

Application Code Manager (localhost:SQLACM.ACM)

FILE EDIT TOOLS VIEW HELP

**System View**

- Project - HTTP
  - Historian
  - HMI
  - Used Libraries

**Controller Preview**

- Controllers
  - PLC
    - Controller Fault Handler
    - Power-Up Handler
    - Tasks
      - ms0008p08
      - ms0016p10
      - ms0048p12
      - ms0064p14
      - ms0128p09
      - ms0256p15
    - SafetyTask
      - SafetyProgram
        - MainRoutine
      - Unscheduled
      - Unscheduled Rou
    - Motion Groups
      - UngruopedAxes
    - Assets
    - I/O Configuration

**Class View**

- Controllers
  - PLC
    - Program (1.0)
      - SafetyProgram
    - Task (1.0)

**Name:** HTTP

**Description:**

**Catalog Number:**

**Solution:**

**Parameters**

**Registered Libraries**

- Registered Libraries
  - (RA-LIB) ACM 2.00 (10)
  - (RA-LIB) Common (22)
    - Asset-Control (10)
    - Operation (6)
      - CommHTTP (2)
        - rac\_LD\_HTTP\_Client (1.0)
        - rac\_LD\_HTTP\_Methods (1.0)
      - CommMQTT (2)
    - DataCollection (2)
    - Technology (6)
    - (RA-LIB) Device (70)
    - (RA-LIB) Machine (370)
    - (RA-LIB) Robotics (48)
    - Robot Catalogs (24)


**Library Repositories**

- Library Repositories

Version 4.03.01 Apply

Now let's add the library

Select the controller and right mouse click and select Add



And select a library

Object Configuration Wizard ? ×

Select a library

Filter:  ☐ Show All Revisions ☐ Show All Libraries

Solution	LibraryType	Category	CatalogNumber	Family	ContentType	Class	Status
<input type="checkbox"/> 1734-Communication							(4 items)
<input type="checkbox"/> 1734-IO							(58 items)
<input type="checkbox"/> 1769-Communication							(2 items)
<input type="checkbox"/> 1769-IO							(62 items)
<input type="checkbox"/> 5000-Communication							(2 items)
<input type="checkbox"/> 5000-IO							(30 items)
<input type="checkbox"/> Asset							(2 items)
<input type="checkbox"/> AxisHdlr-Common							(1 item)
<input type="checkbox"/> AxisHdlr-Handler							(4 items)
<input type="checkbox"/> AxisHdlr-Language							(1 item)
<input type="checkbox"/> CamCalculation							(2 items)
<input type="checkbox"/> CommHTTP							(3 items)
<input type="checkbox"/> CommMOT							(3 items)
<input type="checkbox"/> Contactor							(4 items)

<  >

Cancel << Previous Next >> Finish

Select the client library

Object Configuration Wizard ? X

**Select a library**

Filter:  ☐ Show All Revisions ☐ Show All Libraries

Solution	LibraryType	Category	CatalogNumber	Family	ContentType	Class
[-] AxisHdlr-Language (1 item)						
[-] CamCalculation (2 items)						
[-] CommHTTP (3 items)						
(RA-LIB) Common Operation		CommHTTP	raC_LD_HTTP_Client ( 1.0 )	Logix	Routine	Standard
(RA-LIB) Common Operation		CommHTTP	raC_LD_HTTP_Methods ( 1.0 )	Logix	Routine	Standard
(RA-LIB) Common Asset-Control		CommHTTP	raC_Opr_HTTP ( 1.0 )	Logix	Task	Standard
[-] CommMOTT (3 items)						
[-] Contactor (4 items)						
[-] Conveyor (6 items)						
[-] DataCollection (4 items)						
[-] Device Management (17 items)						
[-] Dosing (3 items)						
[-] EquipmentIndicators (2 items)						
[-] EquipmentPerformance (4 items)						
[-] Event (9 items)						

Click on next

Object Configuration Wizard

**Name:** raC\_LD\_HTTP\_Client

**Description:** HTTP Client

**Catalog Number:** raC\_LD\_HTTP\_Client (1.0) - Put

**Solution:** (RA-LIB) Common Task: Program:

Parameters Linked Libraries

00 General

RoutineName	raC_LD_HTTP_Client
TagName	raC_LD_HTTP_Client
ControllerType	1756-L8x
BackplaneCommCard	False

01 Configuration

URL	http://myhost:8080
UserAgent	
CustomHeader	
UseKeepAlive	False
QueueSize	2
MSGTimeout	1000
CmdTimeout	5000

**RoutineName**  
Insert Routine Name. Routine will be created and Object implement rung inserted. A JSR will be inserted in MainRoutine. If routine name ...

Cancel << Previous Next >> Finish

Enter the parameters like controller type, url (where the API Rest server lies, we will use node-red), etc

<b>Name:</b>	raC_LD_HTTP_Client		
<b>Description:</b>	HTTP Client		
<b>Catalog Number:</b>	raC_LD_HTTP_Client (1.0) - Put		
<b>Solution:</b>	(RA-LIB) Common	<b>Task:</b>	
		<b>Program:</b>	

Parameters Linked Libraries

00 General

RoutineName	raC_LD_HTTP_Client
TagName	raC_LD_HTTP_Client
ControllerType	5069

01 Configuration

URL	http://192.168.1.163:1880/plc
UserAgent	Test
CustomHeader	
UseKeepAlive	False
QueueSize	2
MSGTimeout	1000
CmdTimeout	5000

**UserAgent**  
The User Agent Identifier to send with requests. Leave empty to use default.

Cancel << Previous Next >> Finish

Attention, the URL is without any resource. Correct this



**Name:** raC\_LD\_HTTP\_Client

**Description:**

**Catalog Number:** raC\_LD\_HTTP\_Client (1.0) - Publisher

**Solution:** (RA-LIB) Common      Task:       Program:

---

Parameters    Linked Libraries

▼ 00 General	
RoutineName	raC_LD_HTTP_Client
TagName	raC_LD_HTTP_Client
ControllerType	5069
▼ 01 Configuration	
URL	http://192.168.1.163:1880
UserAgent	Test
CustomHeader	
UseKeepAlive	False
QueueSize	2
MSGTimeout	1000
CmdTimeout	5000

**URL**

URL to the server without any resource. E.g.: http://myServer:8080

Click on Next

Click on Auto


Risoul Ibérica SL

Click OK to create the instantiation


Object Configuration Wizard

**Name:** raC\_LD\_HTTP\_Client  
**Description:** HTTP Client  
**Catalog Number:** raC\_LD\_HTTP\_Client (1.0) - Put  
**Solution:** (RA-LIB) Common **Task:**  **Program:**

Parameters Linked Libraries

 Auto

▼ Linked Libraries

raC\_Opr\_HTTP \*  raC\_Opr\_HTTP

**raC\_Opr\_HTTP**  
CatalogNumber: raC\_Opr\_HTTP, Family: Logix, Solution: (RA-LIB) Common, LibraryType: Asset-Control, Category: CommHTTP, Revision: 1

Cancel << Previous Next >> Finish

Select a task

Object Configuration Wizard



**Name:** raC\_LD\_HTTP\_Client  
**Description:** HTTP Client  
**Catalog Number:** raC\_LD\_HTTP\_Client (1.0) - Put  
**Solution:** (RA-LIB) Common      **Task:** ms0016p10      **Program:**

Parameters    **Linked Libraries**    Auto

▼ **Linked Libraries**  
raC\_Opr\_HTTP      \* raC\_Opr\_HTTP

**raC\_Opr\_HTTP**  
CatalogNumber: raC\_Opr\_HTTP, Family: Logix, Solution: (RA-LIB) Common, LibraryType: Asset-Control, Category: CommHTTP, Revision: 1

Cancel    << Previous    Next >>    Finish

And create a program

And click on finish

Object Configuration Wizard

**Name:**

**Description:**

**Catalog Number:** rogram (1.0) - Pending

**Solution:** System **Task:**

Parameters

Configuration

Type	Program
InhibitProgram	False
SynchronizeRedundancyDataAfterExecution	False
MainRoutineName	MainRoutine
MainRoutineType	RLL
FaultRoutineName	
Class	Standard

General

UseAsFolder	False
-------------	-------

Type

Program Type

Cancel << Previous Next >> Finish

Click on finish

<b>Name:</b>	raC_LD_HTTP_Client		
<b>Description:</b>	HTTP Client		
<b>Catalog Number:</b>	raC_LD_HTTP_Client (1.0) - Put		
<b>Solution:</b>	(RA-LIB) Common	<b>Task:</b>	ms0016p10
		<b>Program:</b>	Program

Parameters

Linked Libraries

Auto

▼ Linked Libraries

raC\_Opr\_HTTP \*

raC\_Opr\_HTTP

raC\_Opr\_HTTP

CatalogNumber: raC\_Opr\_HTTP, Family: Logix, Solution: (RA-LIB) Common, LibraryType: Asset-Control, Category: CommHTTP, Revision: 1

Cancel

<< Previous

Next >>

Finish

Look at the created program

FILE EDIT TOOLS VIEW HELP

System View

- Project - HTTP
  - Historian
  - HMI
  - Used Libraries

Controller Preview

- Controllers
  - PLC
    - Controller Fault Handler
    - Power-Up Handler
  - Tasks
    - ms0008p08
    - ms0016p10
      - Program
        - MainRoutine
        - raC\_LD\_HTTP\_Client
    - ms0048p12
    - ms0064p14
    - ms0128p09
    - ms0256p15
  - SafetyTask
    - SafetyProgram
      - MainRoutine
  - Unscheduled
    - Unscheduled Routines
  - Motion Groups
    - UngroupedAxes
  - Assets
  - I/O Configuration


Class View

- Controllers
  - PLC
    - Program (1.0)
      - Program
      - SafetyProgram
    - raC\_LD\_HTTP\_Client (1.0)
      - raC\_LD\_HTTP\_Client
    - raC\_Opr\_HTTP (1.0)
      - raC\_Opr\_HTTP
    - Task (1.0)

Now let's add the Http Methods on same program

Add New ...





Select and click on Next

Object Configuration Wizard ? ×

Select a library

Filter:  ☐ Show All Revisions ☐ Show All Libraries

Solution	LibraryType	Category	CatalogNumber	Family	ContentType	Class
[-] AxisHdlr-Languane (1 item)						
[-] CamCalculation (2 items)						
[-] CommHTTP (3 items)						
(RA-LIB) Common	Operation	CommHTTP	raC_LD_HTTP_Client ( 1.0 )	Logix	Routine	Standard
(RA-LIB) Common	Operation	CommHTTP	raC_LD_HTTP_Methods ( 1.0 )	Logix	Routine	Standard
(RA-LIB) Common	Asset-Control	CommHTTP	raC_Opr_HTTP ( 1.0 )	Logix	Task	Standard
[-] CommMOTT (3 items)						
[-] Contactor (4 items)						
[-] Convevor (6 items)						
[-] DataCollection (4 items)						
[-] Device Management (17 items)						
[-] Dosing (3 items)						
[-] EquipmentIndicators (2 items)						
[-] EquipmentPerformance (4 items)						
[-] Event (9 items)						

< >

Cancel << Previous Next >> Finish

Select the same task and program

Object Configuration Wizard ? X





**Name:** HTTPMethods

**Description:** HTTP command GET, POST, PUT

**Catalog Number:** 3C\_LD\_HTTP\_Methods (1.0) - I

**Solution:** (RA-LIB) Common **Task:** ▼ **Program:** ▼

Parameters Linked Libraries

▼ 00 General

RoutineName	HTTPMethods
IncludeGET	False
IncludePOST	False
IncludePUT	False

**RoutineName**  
Insert Routine Name. Routine will be created and Object implement rung inserted. A JSR will be inserted in MainRoutine. If routine name ...

Cancel
<< Previous
Next >>
Finish

We will include the GET method

So select True

Object Configuration Wizard

**Name:** HTTPMethods

**Description:** HTTP command GET, POST, PUT I

**Catalog Number:** 3C\_LD\_HTTP\_Methods (1.0) - I

**Solution:** (RA-LIB) Common **Task:**  **Program:**

Parameters Linked Libraries

00 General

RoutineName	HTTPMethods
IncludeGET	False
IncludePOST	False
IncludePUT	False

**RoutineName**  
Insert Routine Name. Routine will be created and Object implement rung inserted. A JSR will be inserted in MainRoutine. If routine name ...

Cancel << Previous Next >> Finish

And adjust parameters

## Object Configuration Wizard



<b>Name:</b>	HTTPMethods		
<b>Description:</b>	HTTP command GET, POST, PUT		
<b>Catalog Number:</b>	3C_LD_HTTP_Methods (1.0) - I		
<b>Solution:</b>	(RA-LIB) Common	<b>Task:</b>	
		<b>Program:</b>	

Parameters

Linked Libraries

00 General

RoutineName	HTTPMethods
IncludeGET	True
IncludePOST	False
IncludePUT	False

01 GETConfiguration

GETTagName	HTTPMethodsGET
GETResource	/plc
GETAcceptContentType	plain/text

**GETAcceptContentType**  
Specify the Accept Header of the request. Leave empty to use 'Accept: \*/\*'

Cancel

<< Previous

Next >>

Finish

## Linked Libraries

**Name:** HTTPMethods  
**Description:** HTTP command GET, POST, PUT  
**Catalog Number:** raC\_LD\_HTTP\_Methods (1.0) - I  
**Solution:** (RA-LIB) Common

**Task:** ▼

**Program:** ▼

Parameters Linked Libraries



Auto

▼ Linked Libraries

raC\_Opr\_HTTP

\* raC\_Opr\_HTTP

HTTPClient



Create New Instance...  
Link to Existing Instance...

**HTTPClient**

CatalogNumber: raC\_LD\_HTTP\_Client, Family: Logix, Solution: (RA-LIB) Common, LibraryType: Operation, Category: CommHTTP, Revision...

Cancel

<< Previous

Next >>

Finish

Object Configuration Wizard ? ×

**Name:** HTTPMethods

**Description:** HTTP command GET, POST, PUT

**Catalog Number:** raC\_LD\_HTTP\_Methods (1.0) - I

**Solution:** (RA-LIB) Common **Task:** ▼ **Program:** ▼

Parameters **Linked Libraries** Auto


▼ **Linked Libraries**

raC_Opr_HTTP	*	raC_Opr_HTTP
HTTPClient		raC_LD_HTTP_Client

**HTTPClient**  
CatalogNumber: raC\_LD\_HTTP\_Client, Family: Logix, Solution: (RA-LIB) Common, LibraryType: Operation, Category: CommHTTP, Revision...

Cancel << Previous Next >> Finish

## Object Configuration Wizard



<b>Name:</b>	<input type="text" value="HTTPMethods"/>		
<b>Description:</b>	<input type="text" value="HTTP command GET, POST, PUT"/>		
<b>Catalog Number:</b>	<input type="text" value="3C_LD_HTTP_Methods (1.0) - I"/>		
<b>Solution:</b>	<input type="text" value="(RA-LIB) Common"/>	<b>Task:</b>	<input type="text" value="ms0016p10"/>
		<b>Program:</b>	<input type="text" value="Program"/>

Parameters

Linked Libraries

00 General

RoutineName

HTTPMethods

IncludeGET

True

IncludePOST

False

IncludePUT

False

01 GETConfiguration

GETTagName

HTTPMethodsGET

GETResource

/plc

GETAcceptContentType

plain/text

**GETAcceptContentType**  
Specify the Accept Header of the request. Leave empty to use 'Accept: \*/\*'

Cancel

<< Previous

Next >>

Finish

Click on next and finish



Application Code Manager (localhost\SQLACM.ACM)

FILE EDIT TOOLS VIEW HELP

System View

- Project - HTTP
  - Historian
  - HMI
  - Used Libraries

Controller Preview


- Controllers
  - PLC
    - Controller Fault Handler
    - Power-Up Handler
    - Tasks
      - ms0008p08
      - ms0016p10
        - Program
          - MainRoutine
          - raC\_LD\_HTTP\_Client
          - HTTPMethods
      - ms0048p12
      - ms0064p14
      - ms0128p09
      - ms0256p15
      - SafetyTask
        - SafetyProgram
          - MainRoutine
      - Unscheduled
        - Unscheduled Routines
      - Motion Groups
        - UngroupedAxes
      - Assets
      - I/O Configuration

Class View

- Controllers
  - PLC
    - Program (1.0)
      - Program
      - SafetyProgram
    - raC\_LD\_HTTP\_Client (1.0)
      - raC\_LD\_HTTP\_Client
    - raC\_LD\_HTTP\_Methods (1.0)
      - HTTPMethods
    - raC\_Opr\_HTTP (1.0)
      - raC\_Opr\_HTTP
    - Task (1.0)

Generate the ACD file

With Generate controllers



Save it

Logix Code Generation

Gener...	Name	Save As	Overwrite Existing	ACM Project Data	Create ACD	Status
<input checked="" type="checkbox"/>	PLC	PLC	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	

Save Path: C:\Users\xavier.florensa\Documents\Marketing\Events\Seminari Studio5000 avanzado\Projects\HTTP

Close Cancel Open Folder Generate

Logix Code Generation

Gener...	Name	Save As	Overwrite Existing	ACM Project Data	Create ACD	Status
<input checked="" type="checkbox"/>	PLC	PLC	<input type="checkbox"/>	<input type="checkbox"/>	<input checked="" type="checkbox"/>	L5X Successful [0 seconds] PLC: ACD Successful [8 seconds]

Save Path: C:\Users\xavier.florensa\Documents\Marketing\Events\Seminari Studio5000 avanzado\Projects\HTTP

Finished

Close Cancel Open Folder Generate

Documents > Marketing > Events > Seminari Studio5000 avanzado > Projects > HTTP

Name	Date modified	Type	Size
HTTP	11/1/2023 2:31 PM	File folder	
PLC.ACD	11/1/2023 2:34 PM	Logix Designer Project	4,598 KB
PLC.L5X	11/1/2023 2:34 PM	Logix Designer XML ...	365 KB
PLC_Log	11/1/2023 2:34 PM	Text Document	16 KB

and open it on Studio5000.

To test it let's prepare a simple RESTful API server, for instance one who returns the random value between 1 and 10.

This way with node-RED

127.0.0.1:1880/#flow/2fa30c2db957bbdd

Rockwell Node-RED : node-r... TTN Login TTN Login | Microsoft 365 Microsoft 365 Office Ubuntu HiveMQ

### Node-RED

filter nodes

network

- mqtt in
- mqtt out
- http in
- http response
- http request
- websocket in
- websocket out

[get] /plc

function

http

debug 38

timestamp

random

set flow.IoT\_data

debug

```
1/11/2023, 18:02:22 node: debug 38
msg.payload : Object
{ IoT_data: 4 }

1/11/2023, 18:02:28 node: debug 38
msg.payload : Object
{ IoT_data: 6 }

1/11/2023, 18:02:33 node: debug 38
msg.payload : Object
{ IoT_data: 7 }

1/11/2023, 18:03:17 node: debug 38
msg.payload : Object
{ IoT_data: 8 }
```

And this is how the nodes are configured

### Edit http in node

Delete Cancel Done

#### Properties

Method GET

URL /plc

Name Name

Edit function node

Delete

Cancel

Done

⚙️ Properties

⚙️

📄

🔗

🏷️ Name

Name

📄 ▼

⚙️ Setup

On Start

**On Message**

On Stop

1

var a=flow.get('IoT\_data');

2

msg.payload={IoT\_data:a};

3

return msg;

Edit http response node

Delete

Cancel

Done

⚙ Properties

⚙

📄

🔗

🏷 Name

Name

← Status code

msg.statusCode

☰ Headers

+ add

The messages sent to this node **must** originate from an *http input* node

Edit inject node

Delete

Cancel

Done

⚙ Properties

⚙

📄

🖨

🔑 Name

Name

≡

msg. payload

=

▼ timestamp

×

≡

msg. topic

=

▼ a<sub>z</sub>

×

+ add

inject now

☐ Inject once after

0.1

seconds, then

🔄 Repeat

interval

▼

every

2

↑

↓

seconds

▼

Edit random node

Delete

Cancel

Done

⚙️ Properties

⚙️

📄

🔗

⋮ Property

msg. payload

🔁 Generate

a whole number - integer

▼

⬇ From

1

⬆ To

10

🏷 Name

Name



## Edit change node

Delete
Cancel
Done

⚙️ Properties

📁 Name
Name

☰ Rules

Set ▼
▼ flow. IoT\_data

☰ to the value ▼ msg. payload

☐ Deep copy value

Voilà

The image displays two software interfaces side-by-side. On the left is the Logix Designer - PLC [5069-L320ERMS2 35.11] window. The 'Program - HTTPMethods' tab is active, showing a ladder logic program with a 'CmdHTTPMethodsGET' node. The 'Controller Organizer' on the left shows the project structure, including 'Tasks', 'Parameters and Local', 'MainRoutine', and 'HTTPMethods'. The 'Watch' window at the bottom shows the variable 'HTTPMethodsGET\_Response.Content' with a value of '["IoT\_data":8]'. On the right is the Node-RED interface. The 'REST API' tab is active, showing a flow with a 'get /plc' node connected to a 'function' node. The 'function' node is configured to 'set flow.IoT\_data'. The 'debug' console on the right shows the output of the 'get /plc' node, displaying the IoT\_data value as 4, 6, 7, and 8.

As you can see on this video

<https://youtu.be/UafsIB52IMU>

Xavier Florensa

Automation specialist

Risoul Ibérica SL

next, we want to Inject on InfluxDB directly from PLC

### 1.1. Installing InfluxDB on windows

Using PowerShell in Administrator mode

Download with this command

```
wget https://dl.influxdata.com/influxdb/releases/influxdb2-2.7.3-windows.zip -Use
BasicParsing -OutFile influxdb2-2.7.3-windows.zip

Expand-Archive .\influxdb2-2.7.3-windows.zip -DestinationPath 'C:\Program Files\I
nfluxData\influxdb\'
```

From this guide

<https://portal.influxdata.com/downloads/>

## Start InfluxDB

In **Powershell**, navigate into `C:\Program Files\InfluxData\influxdb` and start InfluxDB by running the `influxd` daemon:

```
> cd -Path 'C:\Program Files\InfluxData\influxdb'
> ./influxd
```

```
> cd -Path 'C:\Program Files\InfluxData\influxdb'
> ./influxd
```

```
cd -Path 'C:\Program Files\InfluxData\influxdb'
```


```
./influxd
```

Open an explorer with localhost and port 8086

Username

xavier

Password




Start building your influxdb use cases


API token

MwQvFkNF8ul\_Yx8327ohwgDG2qHBhO9ZbAqbpFPcFRX6amE9SooSyxAiA9zofuxj8c\_C26cf-zGmMeLyGYKgHA==

Select Quickstart



## 1.2. Inject your first data with node-red



Let's try to inject to INfluxDB using an Http request

Edit influxdb out node

Delete

Cancel

Done

⚙️ Properties

⚙️

📄

🔗

🏷️ Name

Name

📡 Servidor

[v2.0] http://localhost:8086

▼

✎

🏢 Organización

Risoul

🗑️ Bucket

PLC

📶 Medición

plc\_data

🕒 Precisión

Milliseconds (ms)

▼

Xavier Florensa

Automation specialist

Risoul Ibérica SL

Edit influxdb out node > **Edit influxdb node**

Delete Cancel **Update**

**Properties**

Name

Versión

URL

Token

☒ Verificar el certificado del servidor

localhost:8086/orgs/45bd74e06c16b567/data-explorer?fluxScriptEditor

Rockwell Node-RED : node-r... TTN Login TTN Login | Microsoft 365 Microsoft 365 Office Ubuntu HiveMQ Cloud - Fr... MWC Barcelona advancedfactoriesa...

**Data Explorer**

Single Stat CUSTOMIZE Local SAVE AS

1024,00

Query 1 (0.01s) View Raw Data CSV Past 1h SCRIPT EDITOR SUBMIT

FROM Search buckets

PLC

\_monitoring

\_tasks

+ Create Bucket

Filter

\_measurement 1

plc

plc\_data

Filter

\_field 1

Search \_field tag values

IOT\_data

No tag keys found in the current time range

WINDOW PERIOD

CUSTOM AUTO

auto (10s)

Fill missing values

AGGREGATE FUNCTION


CUSTOM AUTO

Now let's try to build the http request ourselves


```
curl -POST "http://127.0.0.1:8086/api/v2/write?org=Risoul&bucket=PLC&precision=s" --header  
"Authorization: Token  
MwQvFkNF8uI_Yx8327ohwgDG2qHBhO9ZbAqbpFPcFRX6amE9SooSyxAiA9zofuxj8c_C26cf-  
zGmMeLyGYKgHA==" --data-raw "plc_data,host=host1 IoT_data=2324"
```



```
Microsoft Windows [Version 10.0.19045.3570]  
(c) Microsoft Corporation. All rights reserved.  
  
C:\Users\xavier.florensa>curl -POST "http://127.0.0.1:8086/api/v2/write?org=Risoul&bucket=PLC&precision=s" --header "Aut  
horization: Token MwQvFkNF8uI_Yx8327ohwgDG2qHBhO9ZbAqbpFPcFRX6amE9SooSyxAiA9zofuxj8c_C26cf-  
zGmMeLyGYKgHA==" --data-raw "plc_data,host=host1 IoT_data=2324"  
  
C:\Users\xavier.florensa>
```



Let's do this from Node-RED



**Edit function node**

Delete Cancel

**Properties**

Name: Set payload and headers

Setup On Start **On Message** On Stop

```

1 msg.payload = "plc_data,host=host1 IoT_data=1234";
2 msg.headers = {};
3 msg.headers['Authorization'] = 'Token MwQvFkNF8uI_Yx8327ohwgDG2qHBh09ZbAqbpFPcFRX6amE9SooSyxAiA9zofuxj8c_C26cf-zGmMeLyGYKgHA==';
4 msg.headers['Content-Type'] = 'text/plain; charset=utf-8';
5 msg.headers['Accept'] = 'application/json';
6 return msg;

```

```

msg.payload = "plc_data,host=host1 IoT_data=1234";
msg.headers = {};
msg.headers['Authorization'] = 'Token
MwQvFkNF8uI_Yx8327ohwgDG2qHBh09ZbAqbpFPcFRX6amE9SooSyxAiA9zofuxj8c_C26cf-
zGmMeLyGYKgHA==';
msg.headers['Content-Type'] = 'text/plain; charset=utf-8';
msg.headers['Accept'] = 'application/json';
return msg;

```

**Edit http request node**

Delete Cancel **Done**

**Properties**

Method: POST

URL: http://127.0.0.1:8086/api/v2/write?org=Risoul&bucket=PLC&precision=s

☐ Enable secure (SSL/TLS) connection

☐ Use authentication

☐ Enable connection keep-alive

☐ Use proxy

☐ Only send non-2xx responses to Catch node

☐ Disable strict HTTP parsing

Return: a UTF-8 string

☐ Enabled



## Success

The top screenshot shows a Node-RED workflow in a web browser. The workflow consists of the following nodes: 'inject' (disabled), 'timestamp', 'Set payload and headers' (function node), 'http request', and 'debug 40'. The 'Set payload and headers' node is configured with a function that sets the payload to 'string[0]'. The 'http request' node is configured with a host of 'localhost:8086' and a path of '/orgs/45bd74e06c16b567/data-explorer?fluxScriptEditor'. The 'debug 40' node outputs the message '4/11/2023, 10:00:45 node: debug 40 msg.payload : string[0]'. The bottom screenshot shows the 'Data Explorer' interface. The main display shows the value '1234,00'. The 'Query 1' section shows the following configuration: 'FROM' is set to 'PLC', 'Filter' is set to '\_measurement', and 'host' is set to 'host1'. The 'WINDOW PERIOD' is set to 'CUSTOM' and 'AGGREGATE FUNCTION' is set to 'CUSTOM'. The 'SCRIPT EDITOR' tab is active, showing the following script: 'SELECT \* FROM PLC WHERE \_measurement = "plc\_data" AND host = "host1"'. The 'SUBMIT' button is visible.

Now, let's try to do this from our PLC

### 1.3. Injecting in InfluxDB directly from PLC

You can see the final result on this video



<https://youtu.be/tDezJRUEjq4>

The test was done with a PLC in DHCP connected to a wireless router thru patchcord cable


PLC has this address: 192.168.10.197

The computer has this Wi-fi address per DHCP: 192.168.10.105


Adjust these values on PLC




And the custom header




And the InfluxDB server IP



Toggle Post bit




It works!!!!



Now let's try with this value

Program - raC_LD_HTTP_Client		
Program - HTTPMethods		
Program Parameters and Local Tags - Program		
Program - MainRoutine		
Scope:	Program	Show: All Tags
Enter Name Filter		
Name	Value	Force
HTTPMethodsPOST.Val_WaitingPos		0
HTTPMethodsPOST.Val_ResponseTime		208
HTTPMethodsPOST.Val_WaitingTime		0
HTTPMethodsPOST.raC_Opr_HTTP_POST		1
HTTPMethodsPOST.ContentType	'text/plain; charset=utf-8'	
HTTPMethodsPOST.Payload	'plc_data,host=host1 IoT_data=2345'	
HTTPMethodsPOST.Payload.LEN	33	
HTTPMethodsPOST.Payload.DATA	{...}	
HTTPMethodsPOST.Resource	'/api/v2/write?org=Risoul&bucket=PLC&precision=s'	
HTTPMethodsPOST.Response	{...}	
raC_LD_HTTP_Client	{...}	

Toggle Post bit



We can also try with this filtering

← → ↻ 🏠 ⓘ 127.0.0.1:8086/orgs/45bd74e06c16b567/data-explorer?fluxScriptEditor

📁 Rockwell 🌐 Node-RED : node-r... 🌐 TTN Login 📁 TTN 🌐 Login | Microsoft 365 🌐 Microsoft 365 Office 📁 Ub

# Data Explorer

Graph CUSTOMIZE

Create a query. Have fun!

Query 1 + View

FROM

Search buckets

PLC

\_monitoring

\_tasks

+ Create Bucket

Filter

\_measurement 2

Search \_measurement tag va

☐ influxdb\_users\_total

☒ mem

☒ plc\_data

☐ qc\_all\_active

☐ qc\_all\_duration secon...


Filter

\_field


Search \_field tag values

IoT\_data

+



Be careful with the comma



So these are the configuration

Watch			
Quick Watch		Enter Quick Watch List N.	
Name	Sc	Value	
▶ HTTPMethodsPOST_Payload	Pr...	'plc_data,host=host1 IoT_data=2345'	
▶ HTTPMethodsPOST_Resource	Pr...	'/api/v2/write?org=Risoul&bucket=PLC&precision=s'	
▶ raC_LD_HTTP_Client_CustHdr	Pr...	'Authorization: Token MwQvFkNF8uI_Yx8327ohwgDG2qHBhO9ZbAqbpFPcFRX6a...	
▶ raC_LD_HTTP_Client_URL	Pr...	'http://192.168.10.105:8086'	

You can see the final result on this video

<https://youtu.be/tDezJRUEjq4>

A cloud database cannot be used since This HTTP does not support secure https calls